certs directory.

```
[student@workstation ~]$ tree certs
certs
- classroom-ca.pem
 control2.lab.example.com.crt
control2.lab.example.com.key
 controller.lab.example.com.crt
 — controller.lab.example.com.key
 db.lab.example.com.crt
— db.lab.example.com.key
— exec1.lab.example.com.crt
 — exec1.lab.example.com.key
 exec2.lab.example.com.crt
 — exec2.lab.example.com.key
 exec3.lab.example.com.crt
 — exec3.lab.example.com.key
 hop1.lab.example.com.crt
 hop1.lab.example.com.key
  hub.lab.example.com.crt
  hub.lab.example.com.key
0 directories, 17 files
```

You do not use all of these files in this exercise.

1.2. The controller directory contains the manifest file to use for subscribing to the automation controller. Use the tree command to verify this.

2. The lab command also downloads the Red Hat Ansible Automation Platform Bundle installer. Extract it. For simplicity, rename the extracted directory to aap2.2-bundle. Change to the directory that contains the extracted contents.

```
[student@workstation ~]$ tar xzf \
> ansible-automation-platform-setup-bundle-2.2.0-6.1.tar.gz
[student@workstation ~]$ mv ansible-automation-platform-setup-bundle-2.2.0-6.1 \
> aap2.2-bundle
[student@workstation ~]$ cd aap2.2-bundle
```

- 3. Modify the inventory file to specify the following details:
  - The three servers to install
  - The passwords for the administrator account on each server
  - The container registry for the automation controller
  - The variables related to the database
  - The variables related to the certificates

3.1. Edit the inventory file to specify the fully qualified domain name (FQDN) of the automation controller, the private automation hub, and the database servers as follows:

Section of the inventory	FQDN
[automationcontroller]	controller.lab.example.com
[automationhub]	hub.lab.example.com
[database]	db.lab.example.com

3.2. Set the values for the following variables related to the automation controller, its container registry, and its database.

Variable	Value
admin_password	redhat
pg_host	db.lab.example.com
pg_password	redhat
registry_url	hub.lab.example.com
registry_username	admin
registry_password	redhat

# **NOTE**

You use the private automation hub as the container registry for the automation controller.

3.3. Set the values for the following variables related to the private automation hub and its database:

Variable	Value
automationhub_admin_password	redhat
automationhub_pg_host	db.lab.example.com
automationhub_pg_password	redhat

3.4. Set the variables for the signed certificates for the controller, hub, and db servers, the associated private keys, and the GLS Training Classroom CA certificate as follows:

Variable	Value
custom_ca_cert	/home/student/certs/classroom-ca.pem
web_server_ssl_cert	/home/student/certs/controller.lab.example.com.crt

Variable	Value
web_server_ssl_key	/home/student/certs/controller.lab.example.com.key
automationhub_ssl_cert	/home/student/certs/hub.lab.example.com.crt
automationhub_ssl_key	/home/student/certs/hub.lab.example.com.key
postgres_use_ssl	True
postgres_ssl_cert	/home/student/certs/db.lab.example.com.crt
postgres_ssl_key	/home/student/certs/db.lab.example.com.key

3.5. When modified, the uncommented content of the inventory file displays as follows:

```
[automationcontroller]
controller.lab.example.com
[automationcontroller:vars]
peers=execution_nodes
[execution nodes]
[automationhub]
hub.lab.example.com
[automationcatalog]
[database]
db.lab.example.com
[sso]
[all:vars]
admin_password='redhat'
pg_host='db.lab.example.com'
pg_port=5432
pg_database='awx'
pg_username='awx'
pg password='redhat'
pg_sslmode='prefer' # set to 'verify-full' for client-side enforced SSL
registry_url='hub.lab.example.com'
registry_username='admin'
registry_password='redhat'
receptor_listener_port=27199
automationhub_admin_password='redhat'
automationhub_pg_host='db.lab.example.com'
automationhub_pg_port=5432
automationhub_pg_database='automationhub'
automationhub_pg_username='automationhub'
automationhub_pg_password='redhat'
automationhub_pg_sslmode='prefer'
automationcatalog_pg_host=''
automationcatalog_pg_port=5432
automationcatalog_pg_database='automationservicescatalog'
automationcatalog_pg_username='automationservicescatalog'
automationcatalog pg password=''
custom ca cert=/home/student/certs/classroom-ca.pem
web server ssl cert=/home/student/certs/controller.lab.example.com.crt
web_server_ssl_key=/home/student/certs/controller.lab.example.com.key
automationhub ssl cert=/home/student/certs/hub.lab.example.com.crt
automationhub ssl key=/home/student/certs/hub.lab.example.com.key
postgres use ssl=True
postgres ssl cert=/home/student/certs/db.lab.example.com.crt
postgres ssl key=/home/student/certs/db.lab.example.com.key
sso keystore password=''
sso_console_admin_password=''
```

Save and close the file.

# NOTE

You can use the ~/install-installation/inventory file for comparison.

#### 4. As the root user, run the installation script.

4.1. Use the sudo command to change to the root user, using student as the password. Change to the /home/student/aap2.2-bundle directory and execute the setup.sh installation script. The script can take up to 20 minutes to complete.

```
[student@workstation aap2.2-bundle]$ sudo -i
[sudo] password for student: student
[root@workstation ~]# cd /home/student/aap2.2-bundle
[root@workstation aap2.2-bundle]# ./setup.sh -e ignore_preflight_errors=true
Using /etc/ansible/ansible.cfg as config file
...output omitted...
controller.lab.example.com : ok=289    changed=136    ...    failed=0    ...    ignored=6
db.lab.example.com
                       : ok=77
                                changed=31
                                           ... failed=0 ... ignored=1
hub.lab.example.com
                     : ok=213 changed=89
                                            ... failed=0 ... ignored=1
localhost
                        : ok=3
                                changed=1
                                            ... failed=0 ... ignored=0
The setup process completed successfully.
[warn] /var/log/tower does not exist. Setup log saved to setup.log.
```

# **IMPORTANT**

You run the installation script as the root user because the root user on the workstation machine has root access to the controller, hub, and db machines in this lab environment.

Failure to run the installation script as the root user in the classroom environment results in the following error messages:

```
fatal: [controller.lab.example.com]: FAILED! => {"changed": false, "ms
g": "UID on remote machine is 1000 (0 required). Check Ansible connectio
n and become settings."}
fatal: [hub.lab.example.com]: FAILED! => {"changed": false, "msg": "UID
on remote machine is 1000 (0 required). Check Ansible connection and bec
ome settings."}
fatal: [db.lab.example.com]: FAILED! => {"changed": false, "msg": "UID o
n remote machine is 1000 (0 required). Check Ansible connection and beco
me settings."}
```

Because the lab environment does not satisfy the minimum memory requirements for the automation controller and the private automation hub, set the <code>ignore\_preflight\_errors</code> Ansible variable to <code>true</code> to ignore prerequisite checks made before installation starts. This should not be set in a production environment.

4.2. After the installer finishes successfully, exit from the root session.

```
[root@workstation aap2.2-bundle]# exit
```

5. On the workstation machine, navigate to the automation controller web UI to finish the initial configuration. Verify that no warning messages are displayed about the authenticity of the certificate for the automation controller.

5.1. Open a browser and navigate to https://controller.lab.example.com (https://controller.lab.example.com). Because you configured the certificate for the automation controller in the inventory file, and because the workstation machine trusts the CA that signed the certificate, no warning message is displayed about the authenticity of the certificate.

# **IMPORTANT**

The machines in the classroom environment trust any certificate signed by the GLS Training Classroom CA. If your organization uses a corporate or an enterprise certificate authority, then you can configure your machines to trust certificates signed by that certificate authority. Copy the file identified by the custom\_ca\_cert variable to the /etc/pki/ca-trust/source/anchors directory and run the update-ca-trust command.

These steps are not necessary if you use certificates signed by a publicly recognizable certificate authority.

- 5.2. Click the lock icon next to the URL, and then on the pop-up menu, verify this is a secure connection.
  - *Optional.* Click **Connection secure**, **More Information**, and then click **View Certificate** to view the certificate.
- 5.3. Log in to the web UI as the admin user with redhat as the password.
- 5.4. The screen automatically displays the option to upload the subscription manifest file. Click **Browse** and select the manifest.zip file located in the /home/student/controller directory. Click **Next**.
- 5.5. Do not make any changes to the **User and Insights analytics** step. Click **Next**.

## **NOTE**

Although the red asterisk in the **Username** and **Password** fields might suggest that it is mandatory to provide your Red Hat credentials, it is not. When you provide the credentials the automation controller can send the collected data to https://cloud.redhat.com (https://cloud.redhat.com). This is not necessary for this exercise.

- 5.6. Click **Submit** to accept the End User License Agreement.
- 5.7. The automation controller web UI displays the Dashboard.

6. On the workstation machine, navigate to the private automation hub web UI to ensure that the installation was successful. Verify that there is no warning message about the authenticity of the certificate for the private automation hub.

- 6.1. Open a new tab in the browser and navigate to https://hub.lab.example.com (https://hub.lab.example.com). As with the controller server, there is no warning message about the authenticity of the certificate. Click the lock next to the URL, and then verify the secure connection on the pop-up menu.
- 6.2. Log in to the web UI as the admin user with redhat as the password.
- 6.3. The private automation hub web UI displays the dashboard.
- 7. As the postgres user on the database server, verify the existence of the awx and the privateautomationhub databases.
  - 7.1. Log in to the db.lab.example.com database server as the student user. Use the sudo command to become the postgres user, and then list the databases using the psql command. Verify that both databases appear in the list.

```
[student@workstation aap2.2-bundle] $ ssh student@db.lab.example.com
Warning: Permanently added 'db.lab.example.com' (ECDSA) to the list of known hosts.
...output omitted...
[student@db ~]$ sudo su - postgres
[sudo] password for student: student
[postgres@db ~]$ psql -U postgres -1
                                     List of databases
                              | Encoding |
                                             Collate
                                                            Ctype
     Name
                    Owner
 automationhub | automationhub | UTF8
                                         | en US.UTF-8 | en US.UTF-8 |
                                         en_US.UTF-8 | en_US.UTF-8 |
               awx
                              UTF8
 awx
                              UTF8
                                         en_US.UTF-8 | en_US.UTF-8 |
 postgres
               postgres
 template0
               postgres
                              UTF8
                                         | en US.UTF-8 | en US.UTF-8 |
 template1
               postgres
                              UTF8
                                         en_US.UTF-8 | en_US.UTF-8 |
(5 rows)
```

7.2. Exit from the postgres session and from the db machine.

```
[postgres@db ~]$ exit
logout
[student@db ~]$ exit
logout
Connection to db.lab.example.com closed.
```

## **Finish**

On the workstation machine, change to the student user home directory and use the lab command to complete this exercise. This step is important to ensure that resources from previous exercises do not impact upcoming exercises.

```
[student@workstation ~] lab finish install-installation
```

This concludes the section.